

Proxmox

How do I make my vServer reachable via an additional IP or NAT?

Note: This article refers only to dedicated servers with a proxmox host system.

VM and CT are named vServer in the following.

Table of Contents

- [Explanation](#)
- [1. additional IP](#)
 - [1.1. order additional IP](#)
 - [1.2. Switch IP to virtualization](#)
 - [1.3. Setting up the IP on the vServer](#)
- [2. NAT](#)
 - [2.1 Create internal bridge](#)

Explanation

There are two ways to set up Internet access on a VM or CT. Here, setting up an additional IP is the simplest and most recommended method.

1. additional IP
2. NAT

1. additional IP

To be able to set up an additional IP on the vServer, proceed as follows:

- 1.1.** order additional IP
- 1.2.** switch IP to virtualization
- 1.3.** Setting up the additional IP on the vServer

1.1. order additional IP

You can order an additional IP address via the central customer management (CCM). To do this, navigate to "Dedicated Root Server".

Proxmox

Dedicated Root-Server



Dedicated Root-Server

Now select the corresponding server contract. You can now order additional IP addresses via the "Add IP address" button.

Net Configuration (IPv4)

Net address	
Gateway	
Subnet mask	255.255.255.255
Connection	200 Mbps (Contracting at 01.04.2021)
Failover-IP	No assigned Failover-IP.
IP-Address	<input type="text"/> <input type="button" value="Main Address"/>

Net configuration	Order IP Address	Failover IP Management
RDNS Management	Manage Bandwidth	

You can use the slider to set the number of IP addresses you need. You will be shown the price before ordering the IP addresses. Via the button "Order IP address" the additional IP addresses are ordered with costs.

Note: If you need more additional IP addresses than you can select, please contact [support](#).

Proxmox

System Information

IP addresses

Traffic Overview

IP-Adresse hinzufügen

Currently available IP-Addresses: 5 + 0

5 31

5

[Order IP-Address](#)

Summary

Proportional Costs 06.04.2021 - 15.04.2021	New Total Price for IP-Addresses monthly from 16.04.2021
0,00 €	0,00 €

[Order IP-Address](#)

In compliance with the directive 2006/112/EC in the modified version, starting 1.1.2015 prices can vary depending on the country of residence of the customer (the prices in the offers are prices for the Federal Republic of Germany and include VAT). If your place of residence is not in Germany, the prices are net.

1.2. Switch IP to virtualization

In order to be able to set up the additional IP on the vServer, this must be changed to "Virtualization" in the ZKM. To do this, navigate to the server contract and select the configuration of the IP addresses there via the "Configuration" button.

Net Configuration (IPv4)

Net address [blurred]

Gateway [blurred]

Subnet mask 255.255.255.255

Connection [blurred]

Failover-IP No assigned Failover-IP.

IP-Address [blurred] [Main Address](#)

[Net configuration](#) | [Order IP Address](#) | [Failover IP Management](#)

[RDNS Management](#) | [Manage Bandwidth](#)

Now set the configuration of "Host route" to "Virtualization" for the additional IP address and save

Page 3 / 7

Proxmox

the setting via the "Apply changes" button.

Note: If the configuration is already set to virtualization, change this to host route, save the setting, and change the configuration back to virtualization.

System Information	IP-Address	Type	Configuration
IP addresses		Primary	
Traffic Overview		Additional	Host Route <input checked="" type="radio"/> Virtualization
		Additional	Host Route <input type="radio"/> Virtualization
		Additional	Host Route <input type="radio"/> Virtualization
		Additional	Host Route <input type="radio"/> Virtualization
		Additional	Host Route <input type="radio"/> Virtualization
		Additional	Host Route <input type="radio"/> Virtualization

Apply for checked IPs: Host Route Virtualization

Apply Changes

1.3. Setting up the IP on the vServer

Debian / Ubuntu < 20.04

Important:

Please enter the correct network interface here. In the example, we use the network interface "eth0" here. The network interface of your server can be named differently.

The following settings are made directly in the vServer. Use the console via Proxmox to connect to the vServer.

The currently used default network interface can be read out with the following command:

```
ip r s | grep default
default via 192.168.178.1 dev eth0 proto static metric 100
```

eth0 -> network interface, this may vary with your server. Use your network interface in the following.

Now open the network configuration file. Usually this is stored under **"/etc/network/interfaces"**. The network configuration must look like this:

```
auto eth0
iface eth0 inet static
address <additional IP-Adresse>
netmask 255.255.255.255
```

Proxmox

gateway <Gateway of the host system>
pointpoint <Gateway of the host system>

After the settings have been made, the network service is restarted.

service networking restart

CentOS

Important:

Please enter the **correct** network interface here. In the example, we use the network interface "eth0" here. The network interface of your server can be named differently.

The following settings are made directly in the vServer. Use the console via Proxmox to connect to the vServer.

The currently used default network interface can be read out with the following command:

```
ip r s | grep default  
default via 192.168.178.1 dev eth0 proto static metric 100
```

eth0 -> network interface, this may vary with your server. Use your network interface in the following.

Now call the file **"/etc/sysconfig/network-scripts/ifcfg-<network-interface>:0**.

example: /etc/sysconfig/network-scripts/ifcfg-eth0:0

The network configuration must look like this:

```
TYPE=Ethernet  
DEVICE=eth0  
BOOTPROTO=static  
NAME=eth0  
ONBOOT=yes  
IPADDR=<additional IP-Adresse>  
GATEWAY=<Gateway of the host system>
```

Now the network service is restarted:

```
/etc/init.d/network/restart
```

Windows

You can make the network settings in Windows via the graphical interface. To do this, navigate to: Network Card Properties -> Internet Protocol, Version 4 (TCP/IPv4) -> Properties.

Here you can now make the IP settings graphically.

Alternatively, this can also be done via the CMD (Windows key +r, enter "cmd" in the search).

Proxmox

In the CMD, run the following command to set the network settings.

```
netsh interface ipv4 set address name="Ethernet" static <additional IP-Adresse> 255.255.255.255  
<Gateway of the host system>
```

To set the DNS servers, the following commands can be used:

```
netsh interface ip set dns "LAN-connection" static 62.141.32.5  
netsh interface ip set dns "LAN-connection" static 62.141.32.4
```

Note: The commands and configurations on the operating systems were tested under Debian 8, CentOS 7, as well as Windows 2012 R2 Standard.

2. NAT

2.1 Create internal bridge

In order to use NAT, another internal bridge must be added to the previously created bridge. For this the file `/etc/network/interfaces` adapted accordingly. (On the Proxmox host)

example: `/etc/network/interfaces`

```
auto vmbr1  
iface vmbr1 inet static  
    address <private IP-Adresse>  
    netmask <Netmask of the IP network>  
    bridge-ports none  
    bridge_stp off  
    bridge_fd 0  
    post-up echo 1 > /proc/sys/net/ipv4/ip_forward
```

This bridge is used by the vServers to connect to the host system.

Now when you create a vServer, the bridge (vmbr1) must be specified.

Last but not least, the required port shares for the vServer are configured on the host system.

Example: The vServer is to be reached via SSH. Here the SSH service on the vServer runs over the default port 22. We now change the forwarding over port 1024.

To do this, edit the `/etc/network/interfaces` file of the host system (proxmox host) and add the following lines at the end:

```
post-up iptables -t nat -A PREROUTING -i vmbr0 -p tcp --dport 1024 -j DNAT --to <private IP address  
of the vServer>:22  
post-down iptables -t nat -D PREROUTING -i vmbr0 -p tcp --dport 1024 -j DNAT --to <private IP  
address of the vServer>:22
```

Note: All ports to be forwarded must be entered in this file.

Explanation of the two commands above:

-i vmbr0 = The interface with the main IP through which the vServer should be accessible.

Proxmox

-p tcp = The protocol to be used.

--dport 1024 = The port which is "received" by the host system.

--<private IP address of the vServer>:22 = To which internal IP this should be forwarded. After the ":" comes the port on which the service can be reached.

As an example, the internal bridge on the host system should now look like this:

```
auto vmbr1
iface vmbr1 inet static
    address <private IP-Adresse>
    netmask <Netmask of the IP network>
    bridge-ports none
    bridge_stp off
    bridge_fd 0
    post-up echo 1 > /proc/sys/net/ipv4/ip_forward
    post-up iptables -t nat -A PREROUTING -i vmbr0 -p tcp --dport 1024 -j DNAT --to <private IP
address of the vServer>:22
    post-down iptables -t nat -D PREROUTING -i vmbr0 -p tcp --dport 1024 -j DNAT --to <private IP
address of the vServer>:22
```

The network service is then restarted.

As a result, you should now be able to reach the host system via SSH at <main IP>:22 and the vServer at <main IP>:1024.

Unique solution ID: #1477

Author: Bettina Brauer

Last update: 2021-05-21 03:27