

# Dedicated Server

## How can I mount a Moonshot Storage (iSCSI) in the Rescue?

### Table of Contents

- [Explanation](#)
  - [1. add internal IP in /etc/network/interfaces](#)
  - [2. start up internal IP](#)
  - [3. install open-iscsi](#)
  - [4. Check /etc/iscsi/iscsid.conf file](#)
  - [5. Testing the connection to the storage](#)
  - [6. Restart Open-iSCSI](#)
  - [7. Login to the storage](#)
  - [8. Mount storage to /mnt](#)

### Explanation

This article describes how to mount the iSCSI storage of a moonshot in rescue mode.

**Note:** Information about IP, user name as well as password of the iSCSI storage, can be found in the ZKM under the item "Network hard disk".

#### 1. add internal IP in **/etc/network/interfaces**

```
auto eth0:0
iface eth0:0 inet static
address
netmask 255.255.252.0
```

#### 2. start up internal IP

```
ifup eth0:0
```

#### 3. install open-iscsi

```
apt-get install open-iscsi -y
```

#### 4. Check **/etc/iscsi/iscsid.conf** file

The following entries are checked in the file:

Page 1 / 2

© 2024 myLoc managed IT <faq@myloc.de> | 27.12.2024 07:48

URL: <https://faq.myloc.de/index.php?action=faq&cat=3&id=166&artlang=en>

# Dedicated Server

```
node.startup = automatic  
node.session.auth.authmethod = CHAP  
node.session.auth.username =  
node.session.auth.password =
```

## 5. Testing the connection to the storage

```
ping -c 3
```

## 6. Restart Open-iSCSI

```
/etc/init.d/open-iscsi restart
```

## 7. Login to the storage

```
iscsiadm -m discovery -t sendtargets -p  
iscsiadm -m node --login
```

You should now be able to see the storage with `fdisk -l`.

## 8. Mount storage to `/mnt`

```
mount /dev/sdb1 /storage
```

If no sda was displayed with "fdisk -l", the specification in the mount command is not "sdb1" but "sda1".

Unique solution ID: #1539

Author: Bettina Brauer

Last update: 2021-06-28 04:35